


Installing Nemetschek IFC Viewer V1.2

Note: Nemetschek IFC Viewer V1.2 runs on Windows XP, Windows Vista and Windows 7.

Note: If you install **Nemetschek IFC Viewer** on a system, where Microsoft Windows Installer 3.0 or later is not present, an installation of Microsoft Windows Installer is required before you start the main IFC Viewer setup. If the computer has Internet access, Microsoft Windows Installer setup usually starts automatically. You need to restart the computer after the installation.

To install Nemetschek IFC Viewer

- 1 Go to www.nemetschek.de/ifc and download the `Nemetschek-IfcViewer-V1.2-Setup.msi` or `Nemetschek-IfcViewer-V1.2-Setup.zip` file, or insert the data medium in the appropriate drive.
- 2 If you are installing from a data medium, Setup usually starts automatically. Otherwise, open **Windows Explorer** and double-click `Nemetschek-IfcViewer-V1.2-Setup.msi`.
The installation program starts.
- 3 Follow the installation dialog. Click **Weiter >** to confirm.
- 4 Select a path in the **Installationsordner wählen** dialog box or click **Weiter >** to confirm the path proposed.



- 5 Click **Weiter >** to confirm the next dialog boxes and click **Schließen** to finish installing.
When the installation is complete, you can immediately use **Nemetschek IFC Viewer**.

Languages

The menus are available in the following languages: *German, English* and *French*. You can use the **Extras – Languages** menu to switch between these languages at any time.

